

DISPLAY PAGE- TRANSPARENT BACKGROUND









When using this view, it is possible to see the desktop and windows behind the SMART Notebook software window. You can continue to interact with the open, transparent page. It is possible to draw in digital ink on a transparent page and to save the notes in the file. In addition, it is possible to display measurement tools, take screen captures, plus much more. If an area of the screen doesn't include any SMART Notebook software objects, you can select and interact with the desktop and applications behind the SMART Notebook software window.

USE VIEW SCREENS BUTTON

† Press or click the **View Screens** button on the **Notebook Toolbar** (see illustration below).












- † The background of the SMART Notebook software window will become transparent.
- † The desktop and program behind the SMART Notebook software will display in the background.
- † Any objects on the .notebook file page remain visible
- † The **Transparent Background Toolbar** will display in the bottom left corner of the window.
- † The table below explains each of the buttons on this toolbar.

Command/Button		Action
Select		Press or click this button to select objects on the current page.
Pens and Highlighters		To write or draw digital ink on the current page, press or click this button.
Previous Page		This button is used to display the previous page in the current file.
Next Page		Use this button to display the next page in the current file.
More Options		To open a menu of options that enable you to add a screen shade, select different digital ink, select a Creative pen style, add straight lines, add shapes, plus more options, press or click this button.
Exit Transparent Background		Press or click this button to return to standard view.
Toolbar Options		This button is used to display additional toolbar buttons.
Close		Press or click this button to close the toolbar.

DISPLAY MORE TOOLBAR BUTTONS

- † Press or click the **Toolbar Options** button.
- † The toolbar will expand to display the toolbar buttons in the table below.

Command/Button		Action
Blank Page		To insert a new blank page into the current file, press or click this button.
Undo		This button is used to reverse the effect of the last action.
Delete		Press or click this button to delete all the selected objects on the page.
Clear Page		To erase all digital ink and delete all objects from the current page, press or click this button.
Screen Capture Toolbar		This button is used to open the Screen Capture Toolbar. For information on working with this toolbar, see the Screen Capture document on the SMART Board Training Web Page.
Insert Ruler		Press or click this button to insert a ruler on the current page.
Insert Protractor		This button is used to insert a protractor on the current page.
Insert Geodreieck Protractor		To insert a Geodreieck protractor on the current page, press or click this button.
Insert Compass		Press or click this button to insert a compass on the current page.

EXIT TRANSPARENT VIEW

Press or click the **Exit Transparent View** button on the **Toolbar**.